

# Installation Prerequisites

This section contains general information on the necessary prerequisites before installing and setting up Natural on a UNIX platform.

This section covers the following topics:

- Installation Package
- Required Memory Space
- Related Software AG Products
  - Natural and Adabas
  - Other Related Software AG Products
  - Entire Net-Work
  - Accessing the Dictionary Server with Natural for Windows
  - Using Natural in Heterogeneous Environments
- Which Installation Method?
- The Natural Distribution Kit

Product-specific installation, configuration and installation verification procedures are described in section Setup and Installation.

## Installation Package

The installation package containing Software AG products is available on ISO 9660 CD-ROM in **cpio** format.

## Required Memory Space

The memory space required by Natural largely depends on the number of users.

The memory space per user is determined by the settings in the NATPARM parameter module, especially by the values of profile parameters such as USIZE and SSIZE.

In addition to the user-specific memory, you require memory for the buffer pool, which is shared among all users.

## Disk Space

Approximately 150 MB of hard-disk space is required for Natural.

## Related Software AG Products

### Natural and Adabas

welche Produkte sollen hier genannt werden?

Adabas SQL Server (ESQ) ?

Natural Security ?

Natural Construct (CST) ?

Entire Access ?

## Other Related Software AG Products

These products are not necessary in order to use Natural 5.1.1, but if they are installed, the following prerequisites must be met.

Product Name (Product ID)	Requirements

## Entire Net-Work

- Entire Net-Work for UNIX 2.2.3 or above ??

## Dummy1

## Which Installation Method?

The installation method you chose depends on whether Natural is already installed at your site. There are three methods available:

- First-time installation
- Updating Natural 5.1.1
- Upgrade from Natural version 4.1.2

### First-Time Installation

If you are installing Natural for the first time or in an environment where Natural is not yet installed, go straight to the section First-Time Installation.

### Updating Natural 5.1.1

If you want to install a new Natural patch level for an installed Natural 5.1.1, refer to the section Updating Natural 5.1.1.

### Upgrade from Natural version 4.1.2

If you want to upgrade from Natural version 4.1.2 to Natural version 5.1., refer to the section xxx.

## The Natural Distribution Kit

```
hier die Struktur von Torsten  
SAG <-----$SAG  
|  
|_  
|  
|_ common
```

## Help Texts -> anpassen oder löschen?

Natural supplies a large number of online help texts as Natural text members with prefix H- in the library SYSDIC. These texts can be customized and extended by the user with the special function Maintain Natural Help Texts.

All help texts with prefix H- are replaced during installation. To prevent user-modified help texts being replaced with new SAG-supplied texts, rename the prefix H- of modified help texts to T-.

If a help text with prefix T- exists, this is always used by the Natural help system instead of the standard help text with prefix H-.